




# Installation Manual

You have received ForexUltimateBot.exe4 file by email right after purchase (if not please contact [support@forexultimatebot.com](mailto:support@forexultimatebot.com)).

Please put this file into MT4 directory – Like it is shown in picture below. You should have path something like this:

**C:\Program Files\MetaTrader\Alpari\experts**

You need to place file ForexUltimateBot.exe4 into “**experts**” folder.



Start your MT4 (if it is started then please close it and start again)

You need to **Drug-and-drop EurUsd currency to trading window** like it is done in screenshot below.

Then **Drug-and-drop ForexUltimateBot from “Expert Advisors” sub-menu** to the trading charts.

Please check the correct check-boxes like it is shown for ForexUltimateBot to start trading.



Press the “Expert advisor” button like, so it would become like on screenshot.

Select the “H1” timeframe (ForexUltimateBot is trading on 1 hour timeframe)

Make sure that the “face” to the right of ForexUltimateBot is “smiling”. **This means that the robot is active and ready to trade.**



# Settings

By default when you are attaching robot to charts you are using default settings. But you also can try to use more aggressive ones, but please do it after you are filling comfortable with the low risk settings (by default).

## Settings description

Setting (default)	Description
Lots=0.1	Trade Lot. For example it is advised to use for \$100 Lots=0.01 lot, for \$2000 Lots=0.2 and so on.
MM=0	Money Management - your lot will be multiplied for every \$1000. For instance if you have \$2000 then your lot will be automatically raised to 0.2. If you have \$300 and Lots=0.01 then your lot will be 0.03. For the first time it is advice to turn MM off (by default) just to used to robot
In_BUY=1	Buy positions are enabled (robot is able to open buy positions)
In_SELL=1	Sell positions are enabled (robot is able to open buy positions)
Aggr_level=0	Aggression level = 0 (zero) means you will have low risk setting. Aggression level 1 means you will have more aggressive approach. For first time it is advice to use Aggression level = 0 (by default)
f1=0.18	Filter 1. It is not advised to change it at all. Only if you are experienced trader and know how to test EA.
f2=0.18	Filter 2. It is not advised to change it at all. Only if you are experienced trader and know how to test EA.
Period_Filtrng=3	Filter 3. It is not advised to change it at all. Only if you are experienced trader and know how to test EA.
SL_bs=122	Stop Lost. Stop lost will be statically during trade (you can change it here). But Take Profit is dynamic, and it is not changeable.
RecoveryMode=0	Recovery Mode. Recovery mode means that if last closed position is negative then your next lot will be doubled (only once, there won't be second multiply). We strongly recommend keep this setting off (by default). It is done only for experience robot traders.
StealthMode=1	In Stealth mode for 3rd parties like brokers or investors would be much harder to define whether you are using FUB, any other robot or trading yourself.
TradeOnFridays=0	Due to the occasional news fridays are known threat to technical analysis. Therefore you could set FUB not to trade on fridays. (0/False - not to trade) (1/True - trade on fidays)
password=12345	Your password. Please contact <a href="mailto:support@forexultimatebot.com">support@forexultimatebot.com</a> to get your live/demo account password. One Copy of Forex Ultimat Bot supports only one Live account, though you can ask for several demos if you like to.

# Thank you!